# Temperature Measurement App on ESP32-devkitC

This guide introduces how to create and commission a temperature measurement app in esp-matter.

## **Prerequisites**

- 1. A PC with WSL/virtual computer installed or a MacBook.
- 2. esp-idf and esp-matter installed on the platform of choice.
- 3. ESP32-devkitC V4.
- 4. Raspberry Pi with installation according to the instructions in raspi.docx.

This guide follows the WSL method as the author has used it.

#### On Windows Machine with WSL Installed

- 1. Install and enable Windows Subsystem for Linux 2 (WSL2).
- 2. Install Ubuntu 20.04 or 22.04 from the Windows App Store.
- 3. Start Ubuntu (search in the start menu) and run the command uname a. It should report a kernel version of 5.10.60.1 or later. If not, upgrade WSL2 by running ws1 --upgrade from Windows PowerShell.
- 4. Windows does not support exposing COM ports to WSL distros. Install usbipd-win on Windows and WSL (usbipd-win WSL Support).
- 5. From this point, the process for setting up esp-matter and building examples is the same as on other hosts.
- 6. Clone the repositories from inside the WSL environment and not inside a mounted directory.

## Set-up at WSL

### Install prerequisites

```
sudo apt update
sudo apt upgrade
sudo apt-get install git wget flex bison gperf python3 python
```

### Download esp-idf repository (run this at home dir)

```
mkdir -p ~/esp
cd ~/esp
git clone --recursive https://github.com/espressif/esp-idf.gi
```

#### Install tools

```
cd ~/esp/esp-idf
./install.sh esp32
```

#### Download esp-matter repository

```
cd esp-idf
source ./export.sh
cd ..

git clone --recursive https://github.com/espressif/esp-matter
cd esp-matter
./install.sh
cd ..
```

Do this every time when opening a new session (Creates venv)

```
cd esp-idf; source ./export.sh; cd ..
cd esp-matter; source ./export.sh; cd ..
```

# **Usage at WSL**

Do this every time when opening a new session (Creates venv)

```
cd esp-idf; source ./export.sh; cd ..
cd esp-matter; source ./export.sh; cd ..
```

Go to the temperature measurement app

```
cd ~/esp/esp-matter/connectedhomeip/connectedhomeip/examples/
```

Make sure that you have shared the USB with usbipd from the host computer. Then open menuconfig with

```
idf.py menuconfig
```

Turn on Wi-Fi from Rendevzeus mode and also change chip-device settings in the Wi-Fi section (ssid and wpa) to corresponding values.

Then go

```
idf.py build flash monitor
```

This should be good at the WSL end.

# Setup at Raspberry Pi

Open chip-tool with

```
./chip-tool interactive start
```

Then choose

```
pairing onnetwork <this can be anything e.g. 1337> <20202021>
```

After this, the monitor at WSL should say that the connection is successful.

Then you can read values by:

```
temperaturemeasurement read measured-value 1337 1
```

Success!